

AtgUpdater

General purpose ATG package updater

Table of contents

1 Overview.....	2
2 Design.....	2
3 Constraints.....	2
3.1 Allowed Child Dependencies.....	2
3.2 Allowed Parent Dependencies.....	3
4 Attributes.....	3
4.1 Defaults for Imported Attributes.....	3
5 Commands.....	3

1. Overview

AtgUpdater: *General purpose ATG package updater*

2. Design

Super Type Updater

Role	Concrete. (Objects can be created.)
Instance Names	Unique
Notification	false
Template Directory	
Data View	Children, proximity: 2
Logger Name	AtgUpdater

3. Constraints

3.1. Allowed Child Dependencies

- [AtgBuilder](#)
- [AtgSite](#)
- DefaultAllowMultiplePackageMatches1
- DefaultDeploymentType1
- DefaultFailIfPackageNotReplaced1
- DefaultPackageName1
- DefaultPackageType1
- DispatchBaseType1
- DispatchChangeDependencies1
- DispatchExecutionStrategy1
- DispatchOptions1
- DispatchResourceName1
- DispatchResourceType1
- DispatchSortOrder1
- DispatchThreadCount1
- MediatorNotificationList1
- UpdaterNotificationList1

1: These types have a *Singleton* constraint. Only one instance may be added as a resource.

3.2. Allowed Parent Dependencies

- Node

4. Attributes

4.1. Defaults for Imported Attributes

Name	Default
defaultAllowMultiplePackageMatches	false
defaultDeploymentType	Deployment
defaultFailIfPackageNotReplaced	true
defaultPackageName	^\$
defaultPackageType	Package
dispatchBaseType	(?:deployment mediator)
dispatchChangeDependencies	false
dispatchExecutionStrategy	nodedispatch
dispatchOptions	
dispatchResourceName	.*
dispatchResourceType	AtgSite
dispatchSortOrder	ascending
mediatorNotificationList	
threadCount	1
updaterNotificationList	

5. Commands

Note:

Commandline options displayed in square brackets "[]" are optional. If an option expects arguments, then angle brackets are shown after the option "<>". Any default value is shown within the brackets.

