

Apache

Manages an Apache HTTP server

Table of contents

1 Overview.....	3
2 Design.....	3
3 Constraints.....	3
3.1 Allowed Child Dependencies.....	3
3.2 Allowed Parent Dependencies.....	3
4 Attributes.....	4
4.1 Defaults for Imported Attributes.....	4
5 Commands.....	4
5.1 Prepare.....	4
5.2 Docs-Generate.....	5
5.3 assertServiceIsDown.....	5
5.4 assertServiceIsUp.....	5
5.5 startService.....	5
5.6 stopService.....	6
6 Related Types.....	6
6.1 ApacheSetting.....	6
6.2 ApacheReconfigure.....	6
6.3 ApacheDocumentRoot.....	7
6.4 ApacheServerRoot.....	8
6.5 ApacheHttpPort.....	8
6.6 ApacheListen.....	9
6.7 ApacheGroup.....	10
6.8 ApacheUser.....	10

6.9 ApacheIconsDir.....	11
6.10 ApacheErrorDir.....	12
6.11 ApacheCgiBin.....	12
6.12 ApacheProxyAjpLocation.....	13
6.13 ApacheProxyAjpWebapp.....	14
6.14 ApacheServerName.....	14
6.15 ApacheLoadModuleJk.....	15
6.16 ApacheLoadModulePhp.....	16
6.17 ApacheServerAdmin.....	17

1. Overview

Apache: *Manages an Apache HTTP server*

2. Design

Super Type Service

Role	Concrete. (Objects can be created.)
Instance Names	Unique
Notification	false
Template Directory	
Data View	Children, proximity: 2
Logger Name	Apache

3. Constraints

3.1. Allowed Child Dependencies

- [ApacheDocumentRoot](#)
- [ApacheHttpPort](#) 1
- [ApacheLoadModuleJk](#)
- [ApacheLoadModulePhp](#)
- [ApacheReconfigure](#) 1
- [ApacheServerAdmin](#) 1
- [ApacheServerName](#) 1
- DefaultDeploymentType1
- DefaultPackageName1
- DefaultPackageType1
- DispatchChangeDependencies1
- [Tomcat](#)
- zip

1: These types have a *Singleton* constraint. Only one instance may be added as a resource.

3.2. Allowed Parent Dependencies

- Node

- Site

4. Attributes

4.1. Defaults for Imported Attributes

Name	Default
ajpPort	8009
apacheReconfigure	true
catalina_base	/usr/local/tomcat
catalina_home	/usr/local/tomcat
dispatchChangeDependencies	false
documentRoot	\${opts.install_root}/htdocs
httpPort	8180
loadmodule_jk	modules/mod_jk.so
loadmodule_php	modules/libphp4.so
serverAdmin	you@example.com
serverName	localhost

5. Commands

Note:

Commandline options displayed in square brackets "[]" are optional. If an option expects arguments, then angle brackets are shown after the option "<>". Any default value is shown within the brackets.

5.1. Prepare

builds the deployment objects

Usage

Prepare

5.1.1. Workflow

1. Install

2. Stop
3. Configure

5.2. Docs-Generate

generates all defined docs

Usage

```
Docs-Generate [-apacheReconfigure <>] [-archivedir  
<${entity.instance.dir}/var>] [-documentRoot <>]
```

Options

Option	Description
apacheReconfigure	<i>determines whether apache will be configured</i>
archivedir	<i>dir to store current output docs</i>
documentRoot	<i>apache doc root</i>

5.3. assertServiceIsDown

checks if service is down

Usage

```
assertServiceIsDown
```

5.4. assertServiceIsUp

checks if service is running

Usage

```
assertServiceIsUp
```

5.5. startService

starts the service

Usage

```
startService [-apache_bin] [-apacheReconfigure <>] [-basedir  
<>]
```

Options

Option	Description
apache_bin	<i>apache bin install directory</i>

apacheReconfigure	<i>determines whether apache will be restarted</i>
basedir	<i>apache server base</i>

5.6. stopService

stops the service

Usage

stopService [-apacheReconfigure <>]

Options

Option	Description
apacheReconfigure	<i>determines whether apache will be restarted</i>

6. Related Types

The following types are defined for use with Apache.

6.1. ApacheSetting

6.1.1. Overview

ApacheSetting: *An Apache configuration setting*

6.1.2. Design

Super Type Setting

Role	Abstract. (Objects cannot be created.)
Instance Names	Unique

6.2. ApacheReconfigure

6.2.1. Overview

ApacheReconfigure: *determines whether to stop and start apache*

6.2.2. Design

Super Type

[ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.2.3. Attributes

6.2.3.1. Exported Attributes

Name	Property
apacheReconfigure	settingValue

6.3. ApacheDocumentRoot

6.3.1. Overview

ApacheDocumentRoot: *Directory from which httpd will serve files*

6.3.2. Design

Super Type

[ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.3.3. Constraints

6.3.3.1. Allowed Parent Dependencies

- [Apache](#)
- [ApacheSystemService](#)

6.3.4. Attributes

6.3.4.1. Exported Attributes

Name	Property
documentRoot	settingValue

6.4. ApacheServerRoot

6.4.1. Overview

ApacheServerRoot: *Directory from which httpd will serve files*

6.4.2. Design

Super Type

[ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.4.3. Constraints

6.4.3.1. Allowed Parent Dependencies

- [Apache](#)
- [ApacheSystemService](#)

6.4.4. Attributes

6.4.4.1. Exported Attributes

Name	Property
serverRoot	settingValue

6.5. ApacheHttpPort

6.5.1. Overview

ApacheHttpPort: *Apache listening port*

6.5.2. Design

Super Type

[ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.5.3. Constraints

6.5.3.1. Allowed Parent Dependencies

- [Apache](#)

6.5.3.2. Allowed Property Values

Property	Allowed Values	Default	Enforced
settingValue	80		false

6.5.4. Attributes

6.5.4.1. Exported Attributes

Name	Property
httpPort	settingValue

6.6. ApacheListen

6.6.1. Overview

ApacheListen: *Apache listener settings*

6.6.2. Design

Super Type

[ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.6.3. Constraints

6.6.3.1. Allowed Parent Dependencies

- [ApacheSystemService](#)

6.6.4. Attributes

6.6.4.1. Exported Attributes

Name	Property
listen	settingValue

6.7. ApacheGroup**6.7.1. Overview**

ApacheGroup: *Apache run-as group*

6.7.2. Design

Super Type
[ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.7.3. Constraints**6.7.3.1. Allowed Parent Dependencies**

- [ApacheSystemService](#)

6.7.4. Attributes**6.7.4.1. Exported Attributes**

Name	Property
group	settingValue

6.8. ApacheUser**6.8.1. Overview**

ApacheUser: *Apache run-as user*

6.8.2. Design

Super Type
[ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.8.3. Constraints

6.8.3.1. Allowed Parent Dependencies

- [ApacheSystemService](#)

6.8.4. Attributes

6.8.4.1. Exported Attributes

Name	Property
user	settingValue

6.9. ApacheIconsDir

6.9.1. Overview

ApacheIconsDir: *Apache icons directory*

6.9.2. Design

Super Type
[ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.9.3. Constraints

6.9.3.1. Allowed Parent Dependencies

- [ApacheSystemService](#)

6.9.4. Attributes

6.9.4.1. Exported Attributes

Name	Property
iconsDir	settingValue

6.10. ApacheErrorDir**6.10.1. Overview**

ApacheErrorDir: *Apache error handlers directory*

6.10.2. Design

Super Type
[ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.10.3. Constraints**6.10.3.1. Allowed Parent Dependencies**

- [ApacheSystemService](#)

6.10.4. Attributes**6.10.4.1. Exported Attributes**

Name	Property
errorDir	settingValue

6.11. ApacheCgiBin**6.11.1. Overview**

ApacheCgiBin: *Apache CGI scripts directory*

6.11.2. Design

Super Type [ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.11.3. Constraints

6.11.3.1. Allowed Parent Dependencies

- [ApacheSystemService](#)

6.11.4. Attributes

6.11.4.1. Exported Attributes

Name	Property
cgiBin	settingValue

6.12. ApacheProxyAjpLocation

6.12.1. Overview

ApacheProxyAjpLocation: *Apache mod_proxy_ajp Location to proxy to Tomcat*

6.12.2. Design

Super Type [ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.12.3. Constraints

6.12.3.1. Allowed Parent Dependencies

- [ApacheSystemService](#)

6.12.4. Attributes

6.12.4.1. Exported Attributes

Name	Property
proxyAjpLocation	settingValue

6.13. ApacheProxyAjpWebapp

6.13.1. Overview

ApacheProxyAjpWebapp: *Apache mod_proxy_ajp Destination Tomcat Webapp*

6.13.2. Design

Super Type
[ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.13.3. Constraints

6.13.3.1. Allowed Parent Dependencies

- [ApacheSystemService](#)

6.13.4. Attributes

6.13.4.1. Exported Attributes

Name	Property
proxyAjpWebapp	settingValue

6.14. ApacheServerName

6.14.1. Overview

ApacheServerName: *The name or address the server uses to identify itself*

6.14.2. Design

Super Type [ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.14.3. Constraints

6.14.3.1. Allowed Parent Dependencies

- [Apache](#)
- [ApacheSystemService](#)

6.14.3.2. Allowed Property Values

Property	Allowed Values	Default	Enforced
settingValue	• localhost		false

6.14.4. Attributes

6.14.4.1. Exported Attributes

Name	Property
serverName	settingValue

6.15. ApacheLoadModuleJk

6.15.1. Overview

ApacheLoadModuleJk: *Used by the LoadModule directive to link in the JK module. Filename is either an absolute path or relative to ServerRoot.*

6.15.2. Design

Super Type [ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.15.3. Constraints

6.15.3.1. Allowed Parent Dependencies

- [Apache](#)

6.15.3.2. Allowed Property Values

Property	Allowed Values	Default	Enforced
settingValue	• modules/mod_jk.		false

6.15.4. Attributes

6.15.4.1. Exported Attributes

Name	Property
loadmodule_jk	settingValue

6.16. ApacheLoadModulePhp

6.16.1. Overview

ApacheLoadModulePhp: Used by the LoadModule directive to link in the PHP module. Filename is either an absolute path or relative to ServerRoot.

6.16.2. Design

Super Type
[ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.16.3. Constraints

6.16.3.1. Allowed Parent Dependencies

- [Apache](#)

6.16.3.2. Allowed Property Values

Property	Allowed Values	Default	Enforced
settingValue	• modules/libphp4		false

6.16.4. Attributes

6.16.4.1. Exported Attributes

Name	Property
loadmodule_php	settingValue

6.17. ApacheServerAdmin

6.17.1. Overview

ApacheServerAdmin: *Email address of the web server administrator*

6.17.2. Design

Super Type

[ApacheSetting](#)

Role	Concrete. (Objects can be created.)
Instance Names	Unique

6.17.3. Constraints

6.17.3.1. Allowed Parent Dependencies

- [Apache](#)
- [ApacheSystemService](#)

6.17.3.2. Allowed Property Values

Property	Allowed Values	Default	Enforced
settingValue	• you@example.com		false

6.17.4. Attributes

6.17.4.1. Exported Attributes

Name		Property	
serverAdmin		settingValue	